

Attribute: Create Attribute

Property

Functions

afx_msg long **OSPropertyUI::CreateMemberAttribute** (LPCTSTR strAttributeName, LPCTSTR strValue)

Create member attribute by name.

afx_msg long **OSPropertyUI::CreateElementAttribute** (LPCTSTR strAttributeName, LPCTSTR strValue)

Create element attribute by name.

Detailed Description

These functions are related to create attribute.

Function Documentation

- ◆ **CreateElementAttribute()**

```
long OSPropertyUI::CreateElementAttribute ( LPCTSTR strAttributeName,  
                                         LPCTSTR strValue )
```

Create element attribute by name.

Parameters

[in] **strAttributeName** Name of the attribute.

[in] **strValue** A string value

Return values

0 OK.

-1 General error.

C++ Syntax

```
// Create element attribute named "EleAttri1".  
long RetVal = OSPropertyUI::CreateElementAttribute((LPCTSTR)"EleAttri1", (LPCTSTR)"A  
string value");
```

VBA Syntax

```
' Create element attribute named "EleAttri1".  
Dim RetVal As long = OSPropertyUI.CreateElementAttribute("EleAttri1", "A string value");
```

See also

[OSPropertyUI::AssignElementAttribute](#)

[OSPropertyUI::DeleteElementAttribute](#)

- ◆ [CreateMemberAttribute\(\)](#)

```
long OSPropertyUI::CreateMemberAttribute ( LPCTSTR strAttributeName,  
                                         LPCTSTR strValue )
```

Create member attribute by name.

Parameters

[in] **strAttributeName** Name of the attribute.

[in] **strValue** A string value

Return values

0 OK.

-1 General error.

C++ Syntax

```
// Create member attribute named "MemAttri1".  
long RetVal = OSPropertyUI::CreateMemberAttribute((LPCTSTR)"MemAttri1", (LPCTSTR)"A  
string value");
```

VBA Syntax

```
' Create member attribute named "MemAttri1".  
Dim RetVal As VARIANT = OSPropertyUI.CreateMemberAttribute("MemAttri1", "A string  
value");
```

See also

[OSPropertyUI::DeleteMemberAttribute](#)

[OSPropertyUI::AssignMemberAttribute](#)